


mtu ValueCare

Up-To-Date

Service Information

SI-2012-MB-02/00

Minidiag 2 Release 5.02.67

<input checked="" type="checkbox"/> Action Required		<input type="checkbox"/> Information Only			Effective: Immediately
<input type="checkbox"/> Global	OR	<input checked="" type="checkbox"/> North America	<input type="checkbox"/> Eastern Europe / CIS	<input type="checkbox"/> China	
		<input checked="" type="checkbox"/> Latin America	<input type="checkbox"/> Mediterranean	<input type="checkbox"/> North East Asia	
			<input type="checkbox"/> Northern / Central Europe	<input type="checkbox"/> South East Asia	
<input type="checkbox"/> Including MTU Onsite Energy		<input type="checkbox"/> Turkey, Middle East, Africa			<input type="checkbox"/> Australia / Pacific
<input checked="" type="checkbox"/> Principals	<input type="checkbox"/> Sales	<input type="checkbox"/> Parts	<input checked="" type="checkbox"/> Service	<input type="checkbox"/> Warranty	<input type="checkbox"/> <u>Special Distribution List: Specify</u>

This communication is to inform MTU distributors and dealers of the release of a new software version (5.02.67) for the Minidiag 2, the hand-held diagnostic tool used with Mercedes-Benz industrial engines.

It is important that every Minidiag 2 is updated to ensure that communication with all ECUs is possible. If the Minidiag 2 is not updated, it will not have the ability to communicate with the newest software versions installed in the ADM 2, ADM 3 and MR2.

Currently software versions 5.02.61 and software version 5.02.64 can communicate with Tier 4i engines (ADM 3 diag version 210 and MR2b software version 23).

Software version 5.02.67 supports MR2b software version 24 which is required for current production ECUs.

Also included in the software version update is an improved fault code text.

The link to download the new software and instructions for updating the tool are located on the MTU Business Portal by following the path below:

Home Page > After Sales > Documents > Technical Documentation > Mercedes Benz > Minidiag Update

Please address any questions regarding this communication to the Distributor Assistance Center at +1 248 560 8200. This communication will be posted on the web within 24 hours.

This communication was issued by department ECNI on October 25, 2012.